

PORTABLE DOCUMENT FORMAT



HEADER

%PDF-1.1 SIGNATURE & VERSION INFORMATION

```

<< [ID VALUE]* >>
1 0 obj
<<
  /Pages 2 0 R
>>
endobj

2 0 obj
<<
  /Type /Pages
  /Count 1
  /Kids [3 0 R]
>>
endobj

3 0 obj
<<
  /Type /Page
  /Contents 4 0 R
  /Parent 2 0 R
  /Resources <<
    /Font <<
      /F1 <<
        /Type /Font
        /Subtype /Type1
        /BaseFont /Arial
      >>
    >>
  >>
endobj

4 0 obj
<< /Length 50 >>
stream
BT
  /F1 110 Tf
  10 400 Td
  (Hello World!)Tj
ET
endstream
endobj
  
```

DICTIONARY << [ID VALUE]* >>

OBJECT REFERENCE: <OBJECT NUMBER> <REVISION NUMBER> R

IDENTIFIER (WITH /)

ARRAY

STREAM PARAMETERS: LENGTH, COMPRESSION....


BEGIN TEXT
FONT F1 (ARIAL) SET TO SIZE 110
MOVE TO COORDINATE 10, 400
OUTPUT TEXT 'HELLO WORLD!'
END TEXT

STRING

BODY

PARSING

%PDF-1. ? IS CHECKED
startxref POINTS TO XREF
xref POINTS TO EACH OBJECT
trailer IS PARSED
REFERENCES ARE FOLLOWED
DOCUMENT IS RENDERED



XREF TABLE

CROSS REFERENCE

```

xref
0 5
0000000000 65535 f
0000000010 00000 n
0000000047 00000 n
0000000111 00000 n
0000000313 00000 n
  
```

CROSS REFERENCES
5 OBJECTS, STARTING AT INDEX 0
(STANDARD FIRST EMPTY OBJECT 0
OFFSET TO OBJECT 1, REV 0
TO OBJECT 2...
3...
4

TRAILER

```

trailer
<<
  /Root 1 0 R
>>

startxref
413
%%EOF
  
```

